



ProDOS 8

#29: Clearing the Backup Needed Bit

Written by: Jim Luther

September 1990

This Technical Note shows how to clear the “backup needed bit” in a directory entry’s **access** byte.

If you are writing a file backup utility program, you probably want to clear the backup needed bit in each directory entry’s **access** byte as you make the backup of the file associated with that directory entry. The **SET_FILE_INFO** MLI call normally sets the backup needed bit of the **access** byte, but how do you clear it? The answer is at location **BUBIT** (\$BF95) on the ProDOS 8 system global page.

BUBIT normally contains the value \$00. When **BUBIT** contains \$00, the **SET_FILE_INFO** MLI call **always** sets the backup needed bit in the directory entry’s **access** byte. However, if the value \$20 is stored in **BUBIT** immediately before calling **SET_FILE_INFO**, the backup needed bit in the directory entry’s **access** byte can be cleared. **BUBIT** is set back to \$00 by the MLI call. The following code example shows how to clear the backup needed bit. Values other than \$20 or \$00 in **BUBIT** are not supported.

; The pathname of the file should be in ThePathname buffer when this code is called!

```
65816 off
longa off
longi off
```

ClearBackupBit start

; System global page locations

```
MLI          equ $BF00          ;MLI call entry point
BUBIT        equ $BF95          ;Backup Bit Disable, SET_FILE_INFO only
```

; MLI call numbers

```
SET_FILE_INFO equ $C3
GET_FILE_INFO equ $C4
```

; set up FileInfoParms for GET_FILE_INFO MLI call

```
lda #$0A
sta param_count
```

; then...

```
jsr MLI          ;get the current file info
dc I1'GET_FILE_INFO'
dc I2'FileInfoParms'
bne Error
```

```

        lda #$20                ;set the backup bit disable bit
        sta BUBIT
        eor #$FF
        and access              ;clear the backup needed bit
        sta access

; set up FileInfoParms for SET_FILE_INFO MLI call
        lda #$07
        sta param_count

; then...
        jsr MLI                 ;set the file info with the file info
        dc i1'SET_FILE_INFO'    ;(clearing only the backup needed bit)
        dc i2'FileInfoParms'
        bne Error
        rts                    ;return to caller

Error    anop                   ;routine to handle MLI errors
        rts

; Parameter block used for GET_FILE_INFO and SET_FILE_INFO MLI calls

FileInfoParms  anop
param_count    ds 1
pathname       dc i2'ThePathname'
access         ds 1
file_type      ds 1
aux_type       ds 2
storage_type   ds 1
blocks_used    ds 2
mod_date       ds 2
mod_time       ds 2
create_date    ds 2
create_time    ds 2

ThePathname    entry
               ds 65            ;store the pathname of the file here

        end

```

Further Reference

- *ProDOS 8 Technical Reference Manual*